

Inware

INWARE
TECHNOLOGIES, INC.

NOVELL GROUPWISE EXTRACTOR



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Table of Contents

INTRODUCTION.....	3
Contact Information	3
ARCHITECTURE	4
E-Mail Shuttle Extractor	4
E-Mail Shuttle Loader.....	4
PREREQUISITES AND SYSTEM REQUIREMENTS	5
Minimum System Requirements.....	6
Migrating to Microsoft Exchange- Prerequisites.....	7
Setting Permissions- Microsoft Exchange 5.5	8
Setting Permissions - Microsoft Exchange 2000/2003.....	9
Setting Permissions - Microsoft Exchange 2007	9
Migrating to Lotus Notes - Prerequisites	10
Migrating to an IMAP-4 System - Prerequisites.....	10
Migrating to Novell GroupWise - Prerequisites	11
INSTALLING THE E-MAIL SHUTTLE	12
Setting E-Mail Shuttle's Permission	13
Identifying or Setting Users' Passwords.....	13
LAUNCHPAD™.....	14
LaunchPad™ - Novell GroupWise Extractor	14
Running the LaunchPad™.....	14
Migrating to Microsoft Exchange.....	17
Migrating to Novell GroupWise	19
Migrating to Lotus Notes	20
Migrating to an IMAP4 System.....	20
Migrating to an IMAP4 System.....	21
APPENDIX A	24
Establish a Logon Profile on the Exchange server: Option 1	24
APPENDIX B	28
Installing the Collaboration Data Objects.....	28
APPENDIX C	30
Extracting from GroupWise Archives	30



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

TROUBLESHOOTING TIPS & FREQUENTLY ASKED QUESTIONS.....	31
Novell GroupWise Extractor	31
Microsoft Exchange Loader.....	32
Notes Loader	34
IMAP Loader	35
GroupWise Loader.....	35



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Introduction

Thank you for choosing the E-Mail Shuttle as your email migration solution. This manual, as well as the software described in it, is furnished under license and may only be used or copied in accordance with the terms of such license. The information in this manual is furnished for informational purposes only, is subject to change without notice, and should not be construed as a commitment by Inware Technologies, Inc. Inware Technologies, Inc. assumes no responsibility or liability for any errors or inaccuracies that may appear in this manual.

Except as permitted by such license, no part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means – electronic, mechanical, recording, or otherwise – without prior written permission from Inware Technologies, Inc..

E-Mail Shuttle, LaunchPad, NameStar, and Bay files are trademarks of Inware Technologies, Inc. All product and company names herein may be trademarks of their respective owners.

If you need assistance or have questions, please do not hesitate to contact us.

Contact Information

Inware Technologies, Inc.
870 111th Avenue N., Suite 8
Naples, Florida 34108
USA

Contact (Sales, General Inquiries, and Customer Service):

Direct: (+1) 239-592-1816

Facsimile: (+1) 239-592-0941

Email: sales@InwareTechnologies.com

Technical Support:

Email: shuttlesupport@InwareTechnologies.com

Phone: (+1) 239-592-1816

Phone: (+1) 407-323-9616



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Architecture

The E-Mail Shuttle was designed with pure performance and data fidelity at the core. Our solution provides an industrial strength tool for managing migrations.

The E-Mail Shuttle considers a migration to consist of two parts – the e-mail system migrated from and the e-mail system migrated to. The E-Mail Shuttle has a corresponding component for each of these two parts – an Extractor to perform the migration from the legacy system and a Loader to perform the migration to the target system.




Figure 1 – E-Mail Shuttle Architecture

E-Mail Shuttle Extractor

The E-Mail Shuttle Extractor extracts data from the legacy e-mail system. After defining users to migrate and the specific location and requirements of data on the legacy system, the E-Mail Shuttle Extractor automatically retrieves the data and places it on a local or network drive.

E-Mail Shuttle Loader

The E-Mail Shuttle Loader loads data to the target e-mail system. After defining the specific locations and requirements of data on the legacy system, the E-Mail Shuttle Loader automatically retrieves the data from the local or network drive and populates the target e-mail system.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Prerequisites and System Requirements

The amount of time that it takes to install the E-Mail Shuttle is heavily dependent on the email systems involved, as well as the environment and the configuration of your migration system. Installation and end-to-end testing can take as little as a half an hour or it could take days. Inware Technologies, Inc. makes no claim as to the amount of time required for installation, testing and production migrations. Should it be required, Inware Technologies Support will make reasonable efforts to assist you in the configuration of each machine within your environment, so that the installation goes as quickly as possible.

The prerequisites listed below must be met according to which system you are migrating to and from. For example, when migrating from Lotus Domino to Microsoft Exchange, be certain that the prerequisites for each of these systems as listed below are met.

This initial configuration is ultimately the hardest part of the process. Once configured and running, sit back and watch the E-Mail Shuttle migrate your data. If you experience problems after meeting these prerequisites, contact our technical support team.

If you have already installed the product, then it is likely that you have met each of the software prerequisites. The key prerequisite remaining will be to ensure that you have administrative access (with an account/profile) to the mailboxes for migration from the legacy system and administrative access (with an account/profile) to the mailboxes for migration to the target system.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Minimum System Requirements

To use the E-Mail Shuttle Novell GroupWise Extractor, you need to meet the following minimum system requirements:

- ❑ E-Mail Shuttle may be installed on a PC with Windows 2000 Pro, Windows XP Pro or Windows Vista.
- ❑ Install the Microsoft .NET framework on the migration PC.
- ❑ Novell GroupWise Client version 5.2 or greater must be installed and configured to allow access to mailboxes on the source GroupWise mail server. Verify that the GroupWise Client can access GroupWise Personal Address Books.
- ❑ Log on to Netware as an administrator in both GroupWise and Netware. If Novell Netware is not being used, then either the user passwords must be known to the administrator or passwords must be reset to a known default prior to migration.
- ❑ Windows 2000 Security Rollup Package, January 2002 or Service Pack 3 (WLDAP32_VERSION "5.0.2195.4436" or higher)
- ❑ 100 MB available hard-disk space for minimum installation. *Optimally, sufficient Hard Disk space should be available on the Migration PC to contain all user data to be migrated. If this is not possible, configuration changes can be made to require less space or a mapped network drive can be used to contain this data, but these measures can reduce performance speed.*



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to Microsoft Exchange- Prerequisites

Prior to running the LaunchPad, the destination accounts must exist in the Active Directory, and must be mail enabled, with Exchange mailboxes. The mailboxes **ARE NOT** automatically created.

Distribution lists are a feature not available in Microsoft Outlook 97 or Outlook 98. Microsoft Outlook 2000 or higher is required to migrate distribution lists.

1. Setup a migration machine running Windows 2000 Professional or Windows XP Professional.
2. Sufficient Hard Disk space should be available on the Migration PC to contain all user data to be migrated. If this is not possible, configuration changes can be made to require less space or a mapped network drive can be used to contain this data, but these measures can reduce performance speed.
3. Install Microsoft Outlook with the optional CDO component. Outlook 2000 or XP are preferred. CDO is a standard component of Outlook 2000 or XP, but is a separate component of Outlook 2007.
4. In Active Directory, create a mail-enabled user named "Eshuttle".




E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Setting Permissions- Microsoft Exchange 5.5

The E-Mail Shuttle requires a profile with administration privileges to extract personal mail from users' mailboxes. This eliminates the need to create profiles for every user being migrated. To log on with the administrator profile either Outlook or Exchange client needs to be installed on the Exchange server. Once installed, a profile should be created and privileges set.

The profile needs at least Service Account Admin role permissions and should have the ability to extract users (needed for directory synchronization) and extract public folders (for public migration/coexistence).



The E-Mail Shuttle will log on using this profile and extract data from the users' mailboxes.

- ❑ Make the Eshuttle user a Service Account Admin at the Site, Server, and Organization level using the Exchange System Manager.
- ❑ On the migration PC, make the Eshuttle user a local administrator.
- ❑ Log on to Active Directory as Eshuttle.
- ❑ Create an Outlook profile named "Eshuttle" that opens the Eshuttle mailbox and verify that this profile functions properly.
- ❑ Install and run the E-Mail Shuttle.




E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Setting Permissions - Microsoft Exchange 2000/2003

An account must be established in the Active Directory listed in the Exchange Domain Servers and Exchange Domain Users group, but cannot appear in the Administrator group.

This account will have the necessary authorization to access the mailboxes for the migration.

- Set the Eshuttle user to be a member of the Exchange Domain Servers group.
- Set rights for Eshuttle using the following KB article:
<http://support.microsoft.com/default.aspx?scid=kb;en-us;821897&Product=exch2003>



Setting Permissions - Microsoft Exchange 2007

An administrative account must be established in the Active Directory. Open the PowerShell on your Exchange 2007 server and run the following command line:

- `Get-mailboxserver <servername> | add-adpermission -user <service account> -accessrights GenericRead, GenericWrite -extendedrights Send-As, Receive-As, ms-Exch-Store-Admin`
- The parts in <> should be changed to represent the indicated values in your environment.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to Lotus Notes - Prerequisites

The version of the Notes Client to be installed on the migration PC should match the version of the Lotus Notes server you will be loading into. Loading into Lotus Notes 7.x or lower is currently supported.

1. Install the Notes Client, R5 or higher preferred.
2. Configure the Notes Client to use an Administrative ID file, and then close the Client. The Notes ID file used for loading needs to have Manager access to all mailboxes in Notes.
3. Verify that the path to the Notes Client directory (generally c:\lotus\notes) is included in the Environment path on the migration PC.
4. Install and run the E-Mail Shuttle.

Migrating to an IMAP-4 System - Prerequisites

There are no prerequisites for migrating to an IMAP-4 Compliant system. The E-Mail Shuttle can function properly with these minimum requirements. Depending on the volume of e-mail and the desire for increased speed and performance, the requirements can change.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to Novell GroupWise - Prerequisites

1. Install the Microsoft .NET framework on the migration machine.
2. Install the GroupWise Client version 6.0 or above.
3. Verify that the GroupWise Client can log on to mailboxes and view Personal Address Books for any given user.
4. If NDS is being used, log on to NDS as an administrator in both NDS and GroupWise.
5. Install and run the E-Mail Shuttle.

Unfortunately, the 5.5.3 and 5.5.4 versions of the GroupWise Client contained bugs as released by Novell. See the following Novell URL to obtain a patch for these. <http://developer.novell.com/support/sample/tids/pgwal001/pgwal001.htm>.

Like other messaging products, GroupWise 5.5 uses MAPI to enable e-mail functionality in Windows applications. MAPI is part of the Windows Messaging System (WMS) and is not included on the Windows 2000 CD or Windows XP CD's.

The version of Windows Messaging included on the GroupWise 5.5 CD (WMS.EXE) is for Windows 95/98 and is NOT compatible with Windows 2000 or XP. The appropriate WMS.EXE must be installed on Windows 2000 or XP BEFORE installing GroupWise 5.5.

See the Novell Knowledgebase article that deals with this issue for details:

<http://support.novell.com/cgi-bin/search/searchtid.cgi?/2955774.htm>




E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Installing the E-Mail Shuttle

First launch the setup.exe that can be downloaded from the Inware Technologies website. Follow the steps below to progress through the Wizard.

1. Welcome screen – Click “Next”.
2. License Agreement – Select agree and click “Next”.
3. Customer Information – Enter your user name, your company name and click “Next”.
4. Choose Destination Location – Choose your installation directory root level. C:\eshuttle is recommended and used throughout this documentation.
5. Select Options – Choose whether to install an extractor, a loader or both. It is strongly recommended that you install both even if you only intend on this pc doing only extractions or only loads. To install both the extractor and loader on a pc without the appropriate clients, cancel the Wizard and relaunch it from a command prompt by running: setup.exe –noprereq
6. Select Extractor Component – Select your source system or systems and click “Next”.



7. Select Loader Component – Select your destination system or systems and click “Next”.
8. Ready to Install the Program – Click “Install”.

(12)



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Setting E-Mail Shuttle's Permission

The E-Mail Shuttle requires a profile with administration privileges to extract personal mail from users' mailboxes. This eliminates the need to create profiles for every user being migrated. To logon with the administrator profile the Novell GroupWise client must be installed.

Once installed, a profile should be created and privileges set. The profile needs at least Service Account Admin role permissions and should have the ability to extract users (needed for directory synchronization) and extract public folders (for public migration/coexistence). The E-Mail Shuttle will logon using this profile and extract data from the users' mailboxes.

Note: The administrator must close the GroupWise client before the start of the extract process. If setting a forwarding address for each user has been specified the utility will open and close the client automatically as it sets a forwarding rule for each user that is migrated.

Identifying or Setting Users' Passwords

Novell GroupWise provides no mechanism for administrators to export user's private e-mail; therefore, the passwords will be necessary to log onto each user's account in order to extract their e-mails. If we do not know the user's password in order to log onto their account, we will first use the Administrator account to set the users password to some predefined value and ensure the user id is unlocked, and then use that new password to log onto the user's account and extract their mail. This will have the side effect of resetting all user passwords as the migration process runs. Since users' mailboxes are also moved to the new system, it is assumed that they will not be logging back onto GroupWise after this program is run, although it is possible to do so.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

LaunchPad™

LaunchPad™ - Novell GroupWise Extractor

The LaunchPad interface walks system administrators through the steps of a complete e-mail migration from any e-mail system to any e-mail system and offers context-sensitive instructions along the way.

A precursor to the LaunchPad™ is the installation of the product, described earlier. The installation process verifies that specific prerequisites are met in order to run the product.

LaunchPad™ is intended to simplify the migration experience by predetermining much of the information needed for the migration. It currently does not reflect all the functionality of the E-Mail Shuttle. There are many advanced features that are not included in LaunchPad™. These Advanced features can be configured using Mission Control.

Running the LaunchPad™

STEP 1-Migrating from Novell GroupWise

Specify the path to the GroupWise Domain database that contains the users you intend to migrate. Specify the GroupWise Post Office that contains the users you intend to migrate.

Common features are configurable through LaunchPad™ by selecting the “**Advanced**” button.

The screenshot shows a dialog box titled "CompuSven E-Mail Shuttle" with a subtitle "GroupWise Legacy System Information". The dialog contains the following elements:


- Instruction: "Specify the path to the GroupWise Domain database that contains the users you intend to migrate. The path may be expressed as a mapped drive or UNC name"
- Input field: A dropdown menu containing the text "\\Test-server-6\SYSTEMMAIL\GWDDOM" and a "Browse..." button to its right.
- Instruction: "Specify the GroupWise Post Office that contains the users you intend to migrate."
- Input field: A dropdown menu containing the text "COMPUSVEN_PO".
- Button: "Advanced..."
- Navigation buttons at the bottom: "< Back", "Next >", "Cancel", and "Help".



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor


STEP 1- Advanced: Filters

Some of the more common features are configurable through LaunchPad™ by selecting the “Advanced” button. Under the Filters tab, administrators can specify which data to migrate whether it is to be all the data or data within a certain range of days and also whether certain datatypes should be migrated. By checking the items, they will be extracted.



STEP 1- Advanced: Options

If we do not know the user’s password in order to log onto their account, we will first use the Administrator account to set the users password to some predefined value and ensure the User ID is unlocked. We will then use that new password to log onto the user’s account and extract their mail. This will have the side effect of resetting all user passwords as the migration process runs.




Since users’ mailboxes are also moved to the new system, it is assumed that they will not be logging back onto GroupWise after this program is run, although it is possible to do so.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

STEP 1 – Advanced: Folders

Under the Folders tab, administrators can specify which Folders to migrate and can also set the default name of the GroupWise systems inbox.





E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to Microsoft Exchange

STEP 2 Exchange Target System Information

When migrating to Microsoft Exchange, the E-Mail Shuttle requires that a Microsoft Outlook profile exists (see Microsoft Exchange Prerequisites-Setting Permissions) with appropriate administrative rights (see appendix B) to access mailboxes. LaunchPad™ requires that you specify the Exchange LDAP server that contains the directory where the users' will be migrated to. This information can be input in as a server name or as an IP address. LaunchPad™ also includes a Quick Search button that will search the local PC, specifically the local Outlook profiles, for the Exchange servers that are available. There is also a Quick Search button to search for available containers available. From here, the E-Mail Shuttle will search the target LDAP server, find the user and migrate data into the appropriate organization.

CompuSven E-Mail Shuttle

Exchange Target System Information

You have chosen to migrate data to Microsoft Exchange 2000. Provide the Microsoft Exchange 2000 target system information.

Specify the name of the Outlook Profile to use in migration.
The profile must have Administrative rights over migration users' mailboxes.

EShuttle

Click Here to Search for Profile Names!

Specify the Exchange migration target server

TEST-SERVER-4

Click Here to Search for Server Names!

Specify the target LDAP container for users to be migrated

DC=test,DC=compusven,DC=com

Click Here to Search for Containers!

Advanced...

< Back Next > Cancel Help



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Exchange Target System Information – Advanced

This advanced option forgoes the SMTP lookup and allows for hard-coding the organization, administrative group and SMTP address convention in determining the target account to migrate the data to.

Exchange Target System Migration Information

Option

Specify how SMTP addresses should be resolved from the legacy system. Choose 'Automatic' to use the SMTP Address from the legacy system.

Lookup target account information using SMTP address (Recommended)

Provide Target Account Information

Specify the Exchange Organization
[Dropdown]

Specify the Exchange servers migration target Administrative Group
[Dropdown]

Specify how users' Exchange account names are to be determined
[Dropdown] Other [Text]

OK Cancel Help



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to Novell GroupWise

STEP 2 GroupWise Target System Information

When loading into GroupWise version 6.0 or higher, the first two fields of this page should be left blank.

The third field requires that you enter the path to the GroupWise Domain database that you intend to migrate users into. Generally this requires a mapped drive to the GroupWise server. The Domain database file is typically named `wpdomain.db` and this field should contain the path to the folder containing that file. By default, it is usually located in a folder named `Mail` on the GroupWise server.

The screenshot shows a dialog box titled "CompuSven E-Mail Shuttle" with a sub-title "GroupWise Target System Information". The main text reads: "You have chosen to migrate data to a Novell GroupWise target system. Provide the following Novell GroupWise system information".

The dialog contains five input fields, each with a dropdown arrow:

- 1. "Specify the path to the root directory of the API directory service. This can be found in the Root Directory for the Directory Services Messages." (This field is currently blank).
- 2. "Specify the path to the root directory of the API directory service. This can be found in the Root Directory for Gateway Messages." (This field is currently blank).
- 3. "Specify the GroupWise Domain that you intend to migrate users to. The name of the Domain is case-sensitive." (This field is currently blank).
- 4. "Specify the GroupWise Post Office that you intend to migrate users to. The name of the Post Office is case-sensitive." (This field is currently blank).
- 5. "Specify how users' GroupWise account names are to be determined". This field has a dropdown menu set to "From Legacy system Account Name", a checkbox for "Other" which is unchecked, and a text input field.

At the bottom of the dialog are four buttons: "< Back", "Next >", "Cancel", and "Help".

The fourth field should contain the name of the GroupWise Post Office that contains the mailboxes you will be loading data into. This field is case sensitive and typically Post Office names in GroupWise are in all caps, for example, `GWCOMPANY_PO`.

The final drop down box should be set to the naming schema of user names in your GroupWise environment. The name format specified here is the one used when logging into the GroupWise mailbox for any given user.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to Lotus Notes

STEP 2 Notes Target System Information

LaunchPad™ requires that you specify the Domino server that contains the directory where the users' will be migrated to. This information can be input in as a server name, an IP address or in hierarchical format. LaunchPad™ also includes a Quick Search button that will search the local PC, specifically the local Notes .ini for the Domino servers that are available.

The E-Mail Shuttle will log-on to the user accounts to migrate the data requiring the path as well as the naming convention for the mail databases (.nsf files).

The screenshot shows a dialog box titled "CompuSven E-Mail Shuttle" with a close button (X) in the top right corner. The main title is "Notes Target System Information". Below the title, there is a message: "You have chosen to migrate data to a Lotus Notes target system. Provide the following Notes system information".

The first section is "Specify the Domino server that you intend to migrate users to. The name of the server is usually written in a hierarchical format. For example: Granite/East/Acme". Below this text is a dropdown menu containing the text "CN=Server3/0=CompuSven". Below the dropdown is a button that says "Click Here to Search for Available Servers!".

The second section is "Specify the path relative to the Domino server where you intend to have users' mail database files created". Below this text is a dropdown menu containing the text "\mail".

The third section is "Specify how the users' Domino account names are to be determined". Below this text is a dropdown menu containing the text "From Legacy system Account Name" and a checkbox labeled "Other" with an empty text field next to it.

At the bottom of the dialog box, there are four buttons: "< Back", "Next >", "Cancel", and "Help".



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Migrating to an IMAP4 System

STEP 2 IMAP Target System Information

Specify the IP address or DNS name of the IMAP server that you are migrating to. Specify the method to be used to determine the users' account names on the target system. Finally, specify the default password to be used to log into the destination mailboxes. IMAP4 provides no mechanism for administrators to import user's private e-mail; therefore, the passwords will be necessary to log onto each user's account in order to import their e-mails.

A screenshot of a Windows-style dialog box titled "CompuSven E-Mail Shuttle". The dialog has a title bar with a close button (X) on the right. The main content area is titled "IMAP Target System Information" and contains the following text: "You have chosen to migrate data to an IMAP4-compliant target system. Provide the following IMAP4-compliant system information". Below this, there are three sections: 1. "Specify DNS name or IP address of the IMAP target server that you intend to migrate users to" followed by a text input field. 2. "Specify how users' IMAP account names are to be determined" followed by a dropdown menu set to "From Legacy system Account Name", a radio button labeled "Other", and an empty text input field. 3. "OPTIONAL: Specify a default password for the IMAP accounts" followed by an empty text input field. At the bottom of the dialog, there are four buttons: "< Back", "Next >", "Cancel", and "Help".



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

STEP 3 Selecting Users to Migrate

Selecting a single user allows a review of the legacy and target system information. When selecting a single user, the information can be changed manually and these changes for that single user persist if multiple users are subsequently selected.


Account User Name	Account
Alberti, Dave	DAlberti
Blanton, Scott	SBlanton
Carpenter, George	GCarpent
CompuSven,	cadminis
Delany, Tom	TDelany
Dudley, Drew	DDudley
Duncan, Denise	DDuncan
Filla, Paul	PFilla
Fitzgerald, Ken	KFitzgeral
James, Jeanne	JJames
James, Sven	Sven
Lavin, Robin	RLavin
Learn, Nancy	NLearn
Lee, Robert	RLee
Mered, David	DMered



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor


STEP 4 Migration Summary and Configuration

After selecting the users, review a summary of what the E-Mail Shuttle will perform and decides whether to launch the E-Mail Shuttle Extractor, Loader or both.



Migration Directories

This advanced feature provides the ability to customize the location of the bay file and log file creation. This feature should only be used when performing customized migrations.






E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

APPENDIX A

Establish a Logon Profile on the Exchange server: Option 1

When prompted by Outlook client to select a Profile Name, select “New”.



When prompted, Select Microsoft Exchange Server and then “Next”.



Provide the Profile Name, same as the NT account with Service Account Admin permissions then “Next”.





E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Provide the server name for the legacy Exchange system and a mailbox name that is consistent with the profile name provided earlier then “Next”.



The establishment of the profile is complete.




E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Establish a Logon Profile on the Exchange server – Option 2


Another way to establish a logon account is to create the profile in the Mail Properties of the systems Control Panel.

From the Start menu: Select Settings → Control Panel → Mail.

From the Mail Properties menu, select “Add”.



Select Microsoft Exchange Server.






E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Provide the server name of the Microsoft Exchange Server and the name of the NT account with Service Account Admin permissions.

Select “Apply”.

Select “OK”.



The establishment of the profile is complete.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor


APPENDIX B

Installing the Collaboration Data Objects


The E-Mail Shuttle requires that the Collaboration Data Objects (CDO) are installed. CDO is not installed as part of a default Outlook install and should be added using the Outlook setup disk. To install CDO:

Run Microsoft Outlook setup

Select Add or Remove Features.




From this list, ensure that the Collaboration Data Objects are installed. If not installed, select Collaboration Data Objects to “Run from My Computer”.





E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

The sample (left) illustrates that Collaboration Data Objects are installed to Run from My Computer.





E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

APPENDIX C

Extracting from GroupWise Archives

Extracting data from GroupWise Archives is very similar the process for extracting data from GroupWise Mailboxes. The limiting factor to extracting from archives is that the user archives must be accessible from the migration PC. Because we access the users' archives with the GroupWise Client, the user account must be configured to open up the GroupWise Archive using *a path that is accurate relative to the Migration PC*. The best way to test this condition is to open up a user account from the client on the Migration PC and then try to view that user's archives. If this is successful, then we can extract the archive data without any further configuration. If the archive data is not found by the client then the path to the user's archives may have to be changed in the client or the archive data itself may have to be moved.

To extract from GroupWise Archives, first verify that the condition above is fulfilled. Then follow the steps below:

- ❶ Run Launchpad as normal and proceed through the source and target system information screens as if you were extracting server based data.
- ❷ At the user selection screen, select the users whose archive data you wish to extract.
- ❸ On the user summary screen, UNCHECK the boxes for "Launch Loader" and "Launch Extractor". Then click finish. This will configure the shuttlin.txt file which is the list of users to be migrated, but will not launch the mailbox extraction.
- ❹ Now run the file "c:\eshuttle\extractor\groupwise\shutraex.exe". This is the archive extractor and it will run using the shuttlin.txt we just created using Launchpad. It will extract out any mail, calendar, contact and task data present in the archives for the selected users.
- ❺ Run the loader for your destination system to load the data into the destination mailboxes. If you wish to load the data into Exchange PST files, be sure the loader is configured in this manner prior to running the loader.



E-MAIL SHUTTLE USER GUIDE:
GroupWise Extractor

Troubleshooting Tips & Frequently Asked Questions

Novell GroupWise Extractor

Q. The GroupWise Loader cannot login initially, but it does login successfully upon subsequent attempts.

A. Increase the value for the PausePasswordReset parameter in Mission Control for the GroupWise Loader.

Q. The GroupWise Extractor is unable to reset the passwords of the mailboxes to be exported.

A. Make sure you can reset the passwords manually. Also make sure you are logged into NDS as an administrator in both Netware and GroupWise.

Q. The GroupWise Extractor cannot extract PABs.

A. If Outlook is on the migration machine, check the services for the Novell Default Settings mail profile and make sure that the Novell PABs service is enabled.

Q. The bodies of very large messages are being truncated by the extractor.

A. This is due to an API limitation of 30,000 characters for message bodies. The API is unable to load message bodies larger than this size and these messages will be truncated. For reference, 30,000 characters is about 7 solid pages of text.

Q. Our organization is not using NDS. Can we still use the E-Mail Shuttle to migrate users to GroupWise?

A. Yes, the E-Mail Shuttle can still migrate users' data, but NDS is required to automatically reset user passwords to a known default. Usually when loading into fresh empty mailboxes, this is not a problem as all mailboxes can be set to an identical default value and the password reset step is not required.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Microsoft Exchange Loader

Q. The Exchange Loader loads mail, but not calendar and a login popup window is displayed when the Calendar Loader is run.

A. The user is most likely not logged on as the Eshuttle user or the Eshuttle user is not a member of the correct domain or the Exchange Domain Servers group. The different data types use different APIs to access the mailboxes so it is possible for mail to work correctly and calendar to have insufficient access rights.

Q. There is no calendar or contacts present in the mailboxes after migration.

A. The Calendar and Contact Loaders are not launched automatically during the migration. Make sure to run the calendar and contact loaders after the mail loader has completed. To launch the calendar loader, run the escalndr.exe from the “eshuttle/loader/exchange” directory and to launch the contact loader, run escontct.exe.

Q. The Loader is unable to login to mailboxes.

A. Make sure you are logged into Windows as the Eshuttle user created above. Make sure that the Eshuttle user is a member of the correct group and is also a member of the same domain as the destination mailboxes.

Q. The Loader is unable to login under Exchange 2003

A. See the KB article above on setting correct rights for 2003. This can sometimes involve more than just setting the user in the Exchange Domain Servers group.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Q. When running under Exchange 2003, the Mail Loader loads for a while, then starts throwing error messages regarding active mail.

A. Consult the Microsoft KB article

<http://support.microsoft.com/default.aspx?scid=kb;en-us;830836> for increasing the default mail and folder quantity limits in Exchange 2003.

Q. When loading mail into PST files, the Mail Loader loads mail for a while, then stops.

A. Outlook 2000 has a 2 GB limit that might only allow for some of the data to be loaded when the bay file is larger than 2 GB. Outlook 2003 has no such size limit and can be used to circumvent this issue.

Q. When loading mail into PST files, the PST files are not being created.

A. Make sure you aren't running the E-Mail Shuttle on the Exchange server or on a Windows server OS. These operating systems have documented problems with PST file creation. Also make sure that the Letter Age field in Mission Control for the Exchange Loader is set to -1 to enable the PST load.

Q. The Loader is unable to login and the GroupWise mail client is on the machine.

A. You may have to split the GroupWise Extractor and Exchange Loader onto two separate machines. To do this, copy the Eshuttle directory onto a machine without GroupWise and use it for your loader machine. You will have to map a drive to the new machine from the loader machine and set the bay file directories to the new machine in order to run the extractor and loader simultaneously. If GroupWise is not part of your migration, this problem can be fixed by uninstalling both the GroupWise mail client and Outlook and then reinstalling Outlook.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Q. The Loader says something about restart key mismatch and will not launch correctly.

A. You need to clean out any restart information using Mission Control for the Loader. This is the EConfig.exe in the “eshuttle/loader/exchange” directory. Click on the Restart button and set all of the File and Key fields to blank and set all of the Record fields to 0. Then re-launch the loader. This is a common problem to see after a permissions problem prevents logging into to the destination mailboxes.

Notes Loader

Q. The Notes Loader cannot login to the users Notes Database.

A. Make sure that the last ID file used to login to the Notes client was an administrative ID file. Also make sure the Notes Client is not open when running the shuttle.

Q. Certain .DLLs are not being located by my system, how can I fix them?

A. The E-Mail Shuttle is looking for .DLLs in the directory or path of your Lotus Notes or Domino Server software. During the install of the product, you provided information that was written to the path of the system. Be certain that this information is correct by: At the DOS prompt (for example, “C:\”), type path and press Enter. The path for the Notes or Domino server should appear in the display. For example on the Domino Server, the default path is “C:\Lotus\Domino\”. For a dedicated migration server running the Notes R5 client, the default path is “C:\Lotus\Notes”.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

IMAP Loader

Q. How can I configure multiple instances of the E-Mail Shuttle to run simultaneously?

A. Copy the distribution into unique directories on the migration server. Each directory should contain the executable files as well as the distinct configuration files for that migration instance.

For example: The E-Mail Shuttle instance managing the migration of the Marketing Department may be located at “C:\eshuttle\Marketing” while the E-Mail Shuttle instance managing the migration of the Human Resources Department may be located at “C:\eshuttle\HumanResources”. Be aware that running multiple copies of the E-Mail Shuttle on a single PC will generally not help throughput due to bandwidth restrictions on a single NIC card.

GroupWise Loader

Q. The GroupWise Loader cannot login initially, but it does login successfully upon subsequent attempts.

A. Increase the value for the PausePasswordReset parameter in Mission Control for the GroupWise Loader.

Q. The GroupWise Loader is unable to reset the passwords of the mailboxes to be imported.

A. Make sure you can reset the passwords manually. Also make sure you are logged into NDS as an administrator in both Netware and GroupWise. If NDS is not being used, password resets must be performed manually prior to loading or the default password for all mailboxes must be known.



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

Q. The GroupWise Loader cannot import Personal Address Books (PABs).

A. If Outlook is on the migration machine, check the services for the Novell Default Settings mail profile and make sure that the Novell PABs service is enabled. Often this can be addressed by separating the extractor and loader to two separate PCs.

Q. The bodies of very large messages are being truncated by the loader.

A. This is due to an API limitation of 30,000 characters for message bodies. The API is unable to load message bodies larger than this size and these messages will be truncated. For reference, 30,000 characters is about 7 solid pages of text.

Q. The Sent Items folder was not migrated or migrated twice.

A. This is due to differences in the way that Sent Items are handled in GroupWise versions 6.5 and above. Earlier versions of GroupWise deal with the Sent Items folder as a view of the Mailbox, where later versions treat Sent Items as a separate folder entirely. This can be adjusted in Mission Control for the GroupWise Loader under the Misc. tab. Check the box labeled "Target GW 6.5 or higher" if you are running version 6.5 or higher.

Q. The days and months are being inverted on message dates.

A. This is due to differences in date formatting in different regions of the world. This can be adjusted in Mission Control for the GroupWise Loader under the Misc. tab. The default is the US standard of (MM/DD/YYYY). Check the box labeled "Date Format (DD/MM/YYYY)" if you are experiencing this problem.

Q. Our organization is not using NDS. Can we still use the GeM Shuttle Manager to migrate users to GroupWise?

A. Yes, the GeM Shuttle Manager can still migrate users data, but NDS is required to automatically reset user passwords to a known default. Usually when loading into fresh empty mailboxes, this is not a problem as all mailboxes



E-MAIL SHUTTLE USER GUIDE: GroupWise Extractor

can be set to an identical default value and the password reset step is not required.