

**Inware**

INWARE  
TECHNOLOGIES, INC.

XANDROS SCALIX EXTRACTOR



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

<b>INTRODUCTION.....</b>	<b>2</b>
Contact Information .....	2
<b>ARCHITECTURE.....</b>	<b>3</b>
E-Mail Shuttle Extractor .....	3
E-Mail Shuttle Loader.....	3
<b>PREREQUISITES AND SYSTEM REQUIREMENTS .....</b>	<b>4</b>
Minimum System Requirements.....	5
Migrating from Scalix - Prerequisites.....	6
Setting Permissions- Scalix.....	7
Migrating to Microsoft Exchange- Prerequisites.....	8
Setting Permissions- Microsoft Exchange 5.5 .....	9
Setting Permissions - Microsoft Exchange 2000/2003.....	10
Setting Permissions - Microsoft Exchange 2007 .....	10
Migrating to Lotus Notes - Prerequisites.....	11
Migrating to an IMAP-4 System - Prerequisites.....	11
Migrating to Novell GroupWise - Prerequisites .....	12
<b>INSTALLING THE E-MAIL SHUTTLE .....</b>	<b>13</b>
<b>LAUNCHPAD™.....</b>	<b>14</b>
LaunchPad™ - Scalix Extractor .....	14
Running the LaunchPad™.....	15
Migrating to Microsoft Exchange.....	18
Migrating to an IMAP4 System.....	20
Migrating to Novell GroupWise .....	21
Migrating to Lotus Notes .....	22
<b>APPENDIX A .....</b>	<b>25</b>
Installing the Collaboration Data Objects.....	25
<b>APPENDIX B .....</b>	<b>27</b>
Extracting from Outlook PST Files. ....	27
<b>TROUBLESHOOTING TIPS &amp; FREQUENTLY ASKED QUESTIONS.....</b>	<b>28</b>
Scalix Extractor.....	28
Microsoft Exchange Loader.....	30
Notes Loader .....	33
IMAP Loader .....	33
GroupWise Loader.....	34



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Introduction

Thank you for choosing the E-Mail Shuttle as your email migration solution.

This manual, as well as the software described in it, is furnished under license and may only be used or copied in accordance with the terms of such license. The information in this manual is furnished for informational purposes only, is subject to change without notice, and should not be construed as a commitment by Inware Technologies, Inc. Inware Technologies, Inc. assumes no responsibility or liability for any errors or inaccuracies that may appear in this manual.

Except as permitted by such license, no part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means – electronic, mechanical, recording, or otherwise – without prior written permission from Inware Technologies, Inc..

E-Mail Shuttle, LaunchPad, NameStar, and Bay files are trademarks of Inware Technologies, Inc. All product and company names herein may be trademarks of their respective owners.

If you need assistance or have questions, please do not hesitate to contact us.

### Contact Information

Inware Technologies, Inc.  
870 111th Avenue N., Suite 8  
Naples, Florida 34108  
USA

Contact (Sales, General Inquiries, and Customer Service):

Direct: (+1) 239-592-1816

Facsimile: (+1) 239-592-0941

Email: [sales@InwareTechnologies.com](mailto:sales@InwareTechnologies.com)

Technical Support:

Email: [shuttlesupport@InwareTechnologies.com](mailto:shuttlesupport@InwareTechnologies.com)

Phone: (+1) 239-592-1816

Phone: (+1) 407-323-9616




## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Architecture

The E-Mail Shuttle was designed with pure performance and data fidelity at the core. Our solution provides an industrial strength tool for managing migrations.

The E-Mail Shuttle considers a migration to consist of two parts: the e-mail system migrated from and the e-mail system migrated to. The E-Mail Shuttle has a corresponding component for each of these two parts – an Extractor to perform the migration from the legacy system and a Loader to perform the migration to the target system.



*Figure 1- E-Mail Shuttle Architecture*

### E-Mail Shuttle Extractor

The E-Mail Shuttle Extractor extracts data from the legacy e-mail system. After defining users to migrate and the specific location and requirements of data on the legacy system, the E-Mail Shuttle Extractor automatically retrieves the data and places it on a local or network drive.

### E-Mail Shuttle Loader

The E-Mail Shuttle Loader loads data to the target e-mail system. After defining the specific locations and requirements of data on the legacy system, the E-Mail Shuttle Loader automatically retrieves the data from the local or network drive and populates the target e-mail system.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

# Prerequisites and System Requirements

The amount of time that it takes to install the E-Mail Shuttle is heavily dependent on the email systems involved, as well as the environment and the configuration of your migration system. Installation and end-to-end testing can take as little as a half an hour or it could take days. Inware Technologies, Inc. makes no claim as to the amount of time required for installation, testing and production migrations. Should it be required, Inware Technologies Support will make reasonable efforts to assist you in the configuration of each machine within your environment, so that the installation goes as quickly as possible.

The prerequisites listed below must be met according to which system you are migrating to and from. For example, when migrating from Lotus Domino to Microsoft Exchange, be certain that the prerequisites for each of these systems as listed below are met.

This initial configuration is ultimately the hardest part of the process. Once configured and running, sit back and watch the E-Mail Shuttle migrate your data. If you experience problems after meeting these prerequisites, contact our technical support team.

If you have already installed the product, then it is likely that you have met each of the software prerequisites. The key prerequisite remaining will be to ensure that you have administrative access (with an account/profile) to the mailboxes for migration from the legacy system and administrative access (with an account/profile) to the mailboxes for migration to the target system.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

# Minimum System Requirements

To use the E-Mail Shuttle Scalix Extractor, you need to meet the following minimum system requirements:

- ❑ E-Mail Shuttle may be installed on a PC with Windows XP Pro, Windows Vista or Windows 7.
- ❑ Microsoft Outlook profile (see appendix A) with appropriate administrative rights (see appendix B) to access mailboxes.
- ❑ Microsoft Outlook w/Collaboration Data Objects (CDO), specify as default e-mail client (see appendix C)
- ❑ Windows 2000 Security Rollup Package, January 2002 or Service Pack 3 (WLDAP32\_VERSION "5.0.2195.4436" or higher)
- ❑ 100 MB available hard-disk space for minimum installation. *Optimally, sufficient Hard Disk space should be available on the Migration PC to contain all user data to be migrated. If this is not possible, configuration changes can be made to require less space or a mapped network drive can be used to contain this data, but these measures can reduce performance speed.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Migrating from Scalix - Prerequisites

Distribution lists are a feature not available in Microsoft Outlook 97 or Outlook 98. Microsoft Outlook 2000 or higher is required to migrate distribution lists.

1. Setup a migration machine running Windows XP Professional, Windows Vista or Windows 7.
2. Sufficient Hard Disk space should be available on the Migration PC to contain all user data to be migrated. If this is not possible, configuration changes can be made to require less space or a mapped network drive can be used to contain this data, but these measures can reduce performance speed.
3. Install Microsoft Outlook with the optional CDO component. Outlook 2000, XP or 2007 are preferred. CDO is a standard component of Outlook 2000 or XP, but is a separate component of Outlook 2007. If you are using Outlook 2007 you can download CDO from the following link: [Outlook 2007 CDO Download](#)
4. Install the Scalix Connector for Outlook. Version 9.4.2 is preferred but later versions of the connector can also work. Some versions of the connector in the 10.x series have been known to have issues.
5. In the Scalix directory, create a mail-enabled administrative account or use the existing administrative account "sxadmin".



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Setting Permissions- Scalix

The E-Mail Shuttle requires a profile with administration privileges to extract personal mail from users' mailboxes. This eliminates the need to create profiles for every user being migrated. To log on with the administrator profile Outlook needs to be installed migration PC. Once installed, a profile should be created and privileges set.

The profile needs at least mboxadmin role permissions and should have the ability to view mail, calendar and contact data from other users' Scalix mailboxes. The sxadmin account as well as any users being migrated must be configured as full, premium Scalix accounts.

The E-Mail Shuttle will log on using this profile and extract data from the users' mailboxes.

- ❶ On the migration PC, verify that the user logged into the migration PC is a local administrator.
- ❷ In the Scalix mail server command shell, enter the command line:  
`ommodu -o sxadmin -c +admin -mboxadmin`
- ❸ Create an Outlook profile named "Eshuttle" that opens the sxadmin mailbox and verify that this profile functions properly.
- ❹ Open the file eshuttle.ini in the Eshuttle\extractor\scalix directory and set the value of the ScalixAdmin parameter with the administrative account name and password as follows:  
`ScalixAdmin=SU=sxadmin;PASS=ThePasswordToYourSxadminAccount`
- ❺ Install and run the E-Mail Shuttle.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

# Migrating to Microsoft Exchange- Prerequisites

Prior to running the LaunchPad, the destination accounts must exist in the Active Directory and must be mail enabled, with Exchange mailboxes. The mailboxes **ARE NOT** automatically created.

Distribution lists are a feature not available in Microsoft Outlook 97 or Outlook 98. Microsoft Outlook 2000 or higher is required to migrate distribution lists.

6. Setup a migration machine running Windows XP Professional, Windows Vista or Windows 7.
7. Sufficient Hard Disk space should be available on the Migration PC to contain all user data to be migrated. If this is not possible, configuration changes can be made to require less space or a mapped network drive can be used to contain this data, but these measures can reduce performance speed.
8. Install Microsoft Outlook with the optional CDO component. Outlook 2000 or XP are preferred. CDO is a standard component of Outlook 2000 or XP, but is a separate component of Outlook 2007. If you are using Outlook 2007 you can download CDO from the following link: [Outlook 2007 CDO Download](#)
9. In Active Directory, create a mail-enabled user named “Eshuttle”.




## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Setting Permissions- Microsoft Exchange 5.5

The E-Mail Shuttle requires a profile with administration privileges to load personal mail to users' mailboxes. This eliminates the need to create profiles for every user being migrated. To log on with the administrator profile either Outlook or Exchange client needs to be installed on the Exchange server. Once installed, a profile should be created and privileges set.

The profile needs at least Service Account Admin role permissions and should have the ability to extract users (needed for directory synchronization) and extract public folders (for public migration/coexistence).



The E-Mail Shuttle will log on using this profile and extract data from the users' mailboxes.

Make the Eshuttle user a Service Account Admin at the Site, Server, and Organization level using the Exchange System Manager.

- ❶ On the migration PC, make the Eshuttle user a local administrator.
- ❷ Log on to Active Directory as Eshuttle.
- ❸ Create an Outlook profile named "Eshuttle" that opens the Eshuttle mailbox and verify that this profile functions properly.
- ❹ Install and run the E-Mail Shuttle.




## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Setting Permissions - Microsoft Exchange 2000/2003

An account must be established in the Active Directory listed in the Exchange Domain Servers and Exchange Domain Users group, but cannot appear in the Administrator group.

This account will have the necessary authorization to access the mailboxes for the migration.

- Set the Eshuttle user to be a member of the Exchange Domain Servers group.
- Set rights for Eshuttle using the following KB article:  
<http://support.microsoft.com/default.aspx?scid=kb;en-us;821897&Product=exch2003>



### Setting Permissions - Microsoft Exchange 2007

An administrative account must be established in the Active Directory. Open the PowerShell on your Exchange 2007 server and run the following command line:

- `Get-mailboxserver <servername> | add-adpermission -user <service account> -accessrights GenericRead, GenericWrite -extendedrights Send-As, Receive-As, ms-Exch-Store-Admin`
- The parts in <> should be changed to represent the indicated values in your environment.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Migrating to Lotus Notes - Prerequisites

The version of the Notes Client to be installed on the migration PC should match the version of the Lotus Notes server you will be loading into. Loading into Lotus Notes 7.x or lower is currently supported.

1. Install the Notes Client, R5 or higher preferred.
2. Configure the Notes Client to use an Administrative ID file, and then close the Client. The Notes ID file used for loading needs to have Manager Access to all mailboxes in Notes.
3. Verify that the path to the Notes Client directory (generally c:\lotus\notes) is included in the Environment path on the migration PC.
4. Install and run the E-Mail Shuttle.

### Migrating to an IMAP-4 System - Prerequisites

There are no prerequisites for migrating to an IMAP-4 Compliant system. The E-Mail Shuttle can function properly with these minimum requirements. Depending on the volume of e-mail and the desire for increased speed and performance, the requirements can change.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

# Migrating to Novell GroupWise - Prerequisites

1. Install the Microsoft .NET framework on the migration machine.
2. Install the GroupWise Client version 6.0 or above.
3. Verify that the GroupWise Client can log on to mailboxes and view Personal Address Books for any given user.
4. If NDS is being used, log on to NDS as an administrator in both NDS and GroupWise.
5. Install and run the E-Mail Shuttle.

Unfortunately, the 5.5.3 and 5.5.4 versions of the GroupWise Client contained bugs as released by Novell. See the following Novell URL to obtain a patch for these.

<http://developer.novell.com/support/sample/tids/pgwal001/pgwal001.htm>.

Like other messaging products, GroupWise 5.5 uses MAPI to enable e-mail functionality in Windows applications. MAPI is part of the Windows Messaging System (WMS) and is not included on the Windows 2000 CD or Windows XP CD's.

The version of Windows Messaging included on the GroupWise 5.5 CD (WMS.EXE) is for Windows 95/98 and is NOT compatible with Windows 2000 or XP. The appropriate WMS.EXE must be installed on Windows 2000 or XP BEFORE installing GroupWise 5.5.

See the Novell Knowledgebase article that deals with this issue for details:

<http://support.novell.com/cgi-bin/search/searchtid.cgi?/2955774.htm>




## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Installing the E-Mail Shuttle

First launch the setup.exe that can be downloaded from the Inware Technologies website. Follow the steps below to progress through the Wizard.

1. Welcome screen – Click next
2. License Agreement – Select agree and click next
3. Customer Information – Enter your user name, your company name and click next.
4. Choose Destination Location – Choose your installation directory root level. C:\eshuttle is recommended and used throughout this documentation.
5. Select Options – Choose whether to install an extractor, a loader or both. It is strongly recommended that you install both even if you only intend on this pc doing only extractions or only loads. To install both the extractor and loader on a pc without the appropriate clients, cancel the Wizard and relaunch it from a command prompt by running: setup.exe –noprereq
6. Select Extractor Component – Select your source system or systems and click “Next”.



7. Select Loader Component – Select your destination system or systems and click “Next”.
8. Ready to Install the Program – Click “Install”.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### **LaunchPad™**

### **LaunchPad™ - Scalix Extractor**

The LaunchPad interface walks system administrators through the steps of a complete e-mail migration from any e-mail system to any e-mail system and offers context-sensitive instructions along the way.

A precursor to the LaunchPad™ is the installation of the product, described earlier. The installation process verifies that specific prerequisites are met in order to run the product.

LaunchPad™ is intended to simplify the migration experience by predetermining much of the information needed for the migration. It currently does not reflect all the functionality of the E-Mail Shuttle. There are many advanced features that are not included in LaunchPad™. These Advanced features can be configured using Mission Control.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Running the LaunchPad™

#### STEP 1-Specifying the Scalix LDAP (Directory) Server Access Parameters

When migrating from Scalix to another system, LaunchPad™ requires that you specify the Scalix LDAP server that contains the directory listing of users' that you intend to migrate. The Scalix LDAP server is almost always the same as the Scalix Mail server itself. This information can be input in as a server name or as an IP address. LaunchPad™ also includes a Quick Search button that will search the local PC, specifically the local Outlook profiles, for the Scalix servers that are available. There is also a Quick Search button to search for available containers available. For Scalix LDAP, the login name, password and domain should normally be left blank and the LDAP container is almost always “**o=scalix**”.

The screenshot shows a dialog box titled "CompuSven E-Mail Shuttle" with a close button (X). The main title is "Exchange Legacy System LDAP (Directory) Server Information" and the subtitle is "Specify the Exchange LDAP (Directory) server access parameters".

The form contains the following fields and buttons:

- Field: "Specify the IP address or DNS name of the Exchange LDAP server" with a dropdown menu containing "TEST-SERVER-1". Below it is a button: "Click Here to Search for Server Names!".
- Field: "Specify the login name for the Exchange LDAP server" with a text box containing "administrator".
- Field: "Specify the login password for the Exchange LDAP server" with a text box containing "\*\*\*\*\*".
- Field: "Specify the login domain for the Exchange LDAP server" with a text box containing "compusven".
- Field: "Specify the LDAP container of the users to be migrated. Example: o=organization" with a dropdown menu containing "o=COMPUSVEN". Below it is a button: "Click Here to Search for Containers!".
- Button: "Advanced..."

At the bottom of the dialog are four buttons: "< Back", "Next >", "Cancel", and "Help".

Common features are configurable through LaunchPad™ by selecting the “Advanced” button.




## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### *STEP 1 Specifying the Exchange LDAP (Directory) Server Access Parameters – “Advanced” Options*

Once you’ve clicked on the “Advanced” button, you’ll notice two tabs: “Filters” and “Options”.

Under the “Filters” tab, administrators can specify whether all data or only data within a certain date range should be migrated.

You may also specify which data types should be included. By checking the items, they will be extracted from the legacy system.






## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

Under the Options tab, administrators can specify whether or not to invoke the NameStar™ technology.

When checked, the SMTP addresses in the messages should be resolved from their x400 addresses.

For example:

/o=MoveMyMail/ou=Site/cn=Recipients  
/cn=Jdoe will be resolved to the  
SMTP address of  
John.Doe@movemymail.com.



This will ensure and enable reply-ability when migrated to the target system.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Migrating to Microsoft Exchange

#### *STEP 2 Exchange Target System Information*

When migrating to Microsoft Exchange, the E-Mail Shuttle requires that a Microsoft Outlook profile exists (see Microsoft Exchange Prerequisites-Setting Permissions) with appropriate administrative rights (see appendix B) to access mailboxes. LaunchPad™ requires that you specify the Exchange LDAP server that contains the directory where the users' will be migrated to. This information can be input in as a server name or as an IP address. LaunchPad™ also includes a Quick Search button that will search the local PC, specifically the local Outlook profiles, for the Exchange servers that are available. There is also a Quick Search button to search for available containers available. From here, the E-Mail Shuttle will search the target LDAP server, find the user and migrate data into the appropriate organization.

A screenshot of the "CompuSven E-Mail Shuttle" application window, specifically the "Exchange Target System Information" dialog box. The dialog box has a title bar with the text "CompuSven E-Mail Shuttle" and a close button. The main content area contains the following text and controls:

Exchange Target System Information

You have chosen to migrate data to Microsoft Exchange 2000. Provide the Microsoft Exchange 2000 target system information.

Specify the name of the Outlook Profile to use in migration.  
The profile must have Administrative rights over migration users' mailboxes.

EShuttle [dropdown menu]

Click Here to Search for Profile Names! [button]

Specify the Exchange migration target server

TEST-SERVER-4 [dropdown menu]

Click Here to Search for Server Names! [button]

Specify the target LDAP container for users to be migrated

DC=test,DC=compusven,DC=com [dropdown menu]

Click Here to Search for Containers! [button]

Advanced... [button]

< Back [button] Next > [button] Cancel [button] Help [button]



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### *Exchange Target System Information – Advanced*

This advanced option forgoes the SMTP lookup and allows for hard-coding the organization, administrative group and SMTP address convention in determining the target account to migrate the data to.

A screenshot of a Windows-style dialog box titled "Exchange Target System Migration Information". The dialog has a tab labeled "Option". Below the title bar, there is a text instruction: "Specify how SMTP addresses should be resolved from the legacy system. Choose 'Automatic' to use the SMTP Address from the legacy system." There are two radio buttons: the first is "Lookup target account information using SMTP address (Recommended)" and is unselected; the second is "Provide Target Account Information" and is selected. Below the selected radio button is a group box containing three fields: "Specify the Exchange Organization" with a dropdown menu, "Specify the Exchange servers migration target Administrative Group" with a dropdown menu, and "Specify how users' Exchange account names are to be determined" with a dropdown menu and a checkbox labeled "Other" next to a text input field. At the bottom of the dialog are three buttons: "OK", "Cancel", and "Help".



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Migrating to an IMAP4 System

#### *STEP 2 IMAP Target System Information*

Specify the IP address or DNS name of the IMAP server that you are migrating to. Specify the method to be used to determine the users' account names on the target system. Finally, specify the default password to be used to log into the destination mailboxes. IMAP4 provides no mechanism for administrators to import user's private e-mail; therefore, the passwords will be necessary to log onto each user's account in order to import their e-mails.

The screenshot shows a dialog box titled "CompuSven E-Mail Shuttle" with a close button (X) in the top right corner. The main title is "IMAP Target System Information". Below the title, there is a message: "You have chosen to migrate data to an IMAP4-compliant target system. Provide the following IMAP4-compliant system information".

The first section is labeled "Specify DNS name or IP address of the IMAP target server that you intend to migrate users to" and contains a text input field with a dropdown arrow on the right.

The second section is labeled "Specify how users' IMAP account names are to be determined" and contains a dropdown menu with "From Legacy system Account Name" selected, a checkbox labeled "Other", and an empty text input field.

The third section is labeled "OPTIONAL: Specify a default password for the IMAP accounts" and contains an empty text input field.

At the bottom of the dialog box, there are four buttons: "< Back", "Next >", "Cancel", and "Help".



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Migrating to Novell GroupWise

#### STEP 2 GroupWise Target System Information

When loading into GroupWise version 6.0 or higher, the first two fields of this page should be left blank.

The third field requires that you enter the path to the GroupWise Domain database that you intend to migrate users into. Generally this requires a mapped drive to the GroupWise server. The Domain database file is typically named `wpdomain.db` and this field should contain the path to the folder containing that file. By default, it is usually located in a folder named `Mail` on the GroupWise server.

The screenshot shows a dialog box titled "CompuSven E-Mail Shuttle" with a sub-header "GroupWise Target System Information". The main text reads: "You have chosen to migrate data to a Novell GroupWise target system. Provide the following Novell GroupWise system information". There are five input fields: 1) "Specify the path to the root directory of the API directory service. This can be found in the Root Directory for the Directory Services Messages." (empty dropdown), 2) "Specify the path to the root directory of the API directory service. This can be found in the Root Directory for Gateway Messages." (empty dropdown), 3) "Specify the GroupWise Domain that you intend to migrate users to. The name of the Domain is case-sensitive." (empty dropdown), 4) "Specify the GroupWise Post Office that you intend to migrate users to. The name of the Post Office is case-sensitive." (empty dropdown), 5) "Specify how users' GroupWise account names are to be determined" with a dropdown set to "From Legacy system Account Name", a radio button for "Other", and an empty text field. At the bottom are buttons for "< Back", "Next >", "Cancel", and "Help".

The fourth field should contain the name of the GroupWise Post Office that contains the mailboxes you will be loading data into. This field is case sensitive and typically Post Office names in GroupWise are in all caps, for example, `GWCOMPANY_PO`.

The final drop down box should be set to the naming schema of user names in your GroupWise environment. The name format specified here is the one used when logging into the GroupWise mailbox for any given user.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Migrating to Lotus Notes

#### *STEP 2 Notes Target System Information*

LaunchPad™ requires that you specify the Domino server that contains the directory where the users' will be migrated to. This information can be input in as a server name, an IP address or in hierarchical format. LaunchPad™ also includes a Quick Search button that will search the local PC, specifically the local Notes .ini for the Domino servers that are available.

The E-Mail Shuttle will log-on to the user accounts to migrate the data requiring the path as well as the naming convention for the mail databases (.nsf files).

**CompuSven E-Mail Shuttle** [X]

**Notes Target System Information**

You have chosen to migrate data to a Lotus Notes target system. Provide the following Notes system information

Specify the Domino server that you intend to migrate users to. The name of the server is usually written in a hierarchical format.  
For example: Granite/East/Acme

Specify the path relative to the Domino server where you intend to have users' mail database files created

Specify how the users' Domino account names are to be determined

Other

< Back   Next >   Cancel   Help



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### STEP 3 Selecting Users to Migrate

Selecting a single user allows a review of the legacy and target system information. When selecting a single user, the information can be changed manually and these changes for that single user persist if multiple users are subsequently selected.

**CompuSven E-Mail Shuttle**

**Accounts to Migrate**  
Select the account(s) to be migrated

Account User Name	Account I
Alberti, Dave	DAlberti
Blanton, Scott	SBlanton
Carpenter, George	GCarpent
CompuSven,	cadminis
Delany, Tom	TDelany
Dudley, Drew	DDudley
Duncan, Denise	DDuncan
Filla, Paul	PFilla
Fitzgerald, Ken	KFitzgeral
James, Jeanne	JJames
James, Sven	Sven
Lavin, Robin	RLavin
Learn, Nancy	NLearn
Lee, Robert	RLee
Merrill, David	DMerrill

Migrating From Domino Account:

Server Name:

Canonical:

DB File Name:

Migrating To Exchange 2000 Account:

SMTP Address:

Select All    Deselect All


< Back    Next >    Cancel    Help



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor


### *STEP 4 Migration Summary and Configuration*

After selecting the users, review a summary of what the E-Mail Shuttle will perform and decide whether to launch the E-Mail Shuttle Extractor, Loader or both.



### *Migration Directories*

This advanced feature provides the ability to customize the location of the bay file and log file creation. This feature should only be used when performing customized migrations.





## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor


# APPENDIX A

## Installing the Collaboration Data Objects


The E-Mail Shuttle Exchange Loader requires that the Collaboration Data Objects (CDO) are installed. CDO is not installed as part of a default Outlook install and should be added using the Outlook setup disk. To install CDO:

Run Microsoft Outlook setup.

Select Add or Remove Features.




From this list, ensure that the Collaboration Data Objects are installed. If not installed, select Collaboration Data Objects to “Run from My Computer”.





## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

The sample (left) illustrates that Collaboration Data Objects are installed to Run from My Computer.





## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

# APPENDIX B

## Extracting from Outlook PST Files.

By creating a specially formatted shuttlin file, it is possible to extract from Outlook PST files. Please see Appendix B for general shuttlin file details.

To extract from PST files, the shuttlin file is formatted exactly like normal, except for two parameters, which must contain special information:

- Server: This parameter must contain the string “PST”.
- Canonical Name: (normally unused) this parameter must contain the full path to the Outlook PST file.
- As stated above, all other parameters are filled in normally.

*Sample of PST shuttlin layout*

*ES\_System^EXCHANGE^*

*ES\_Export^Callen^PST^^C:\Archives\callen.pst^^callen@test.compusven.com  
^Carol^Allen^ callen^COMPUSVEN\_PO^COMPUSVEN\_DOM^DBTitle^*

- ❖ (Extract the data in the file callen.pst to a BAY file formatted for loading into a Novell GroupWise mailbox, where the GroupWise UserID is “callen”, the GroupWise Post office is “COMPUSVEN\_PO”, and the GroupWise Domain is “COMPUSVEN\_DOM”.)

*ES\_System^EXCHANGE^*

*ES\_Export^Callen^PST^^C:\Archives\callen.pst^^callen@test.compusven.com  
^Carol^Allen^ callen^Server3\Compusven^mail\callen.nsf^DBTitle^*

- ❖ (Extract the data in the file callen.pst to a BAY file formatted for loading into a Lotus Domino mailbox, where the Domino UserID is “callen”, the Domino server is “Server3\Compusven”, and the Domino database file is “mail\callen.nsf”.)



E-MAIL SHUTTLE USER GUIDE:  
Xandros Scalix Extractor

## Troubleshooting Tips & Frequently Asked Questions

### Scalix Extractor

**Q.** After migration, the Tos and Froms in the headers appear inverted and the letter time and dates are set to the time of migration when the mail is viewed from Web Access, but everything looks normal when viewed from Outlook.

**A.** *This is an issue with Scalix Web Access. Scalix Support should be contacted for more details. They will most likely recommend reverting back to an earlier version of the Scalix Connector.*

**Q.** The Scalix Loader loads mail, but not the Calendar Loader cannot logon.

**A.** *Try using the Calendar Loader that uses OOM instead of the standard CDO based Calendar Loader. Replace the ESCalndr.exe in the directory c:\eshuttle\loader\scalix with the one in the directory c:\eshuttle\loader\scalix\oom.*

**Q.** The Eshuttle Contact Loader loads contacts are fragmented and only part of each contact entry is loaded.

**A.** *Try using an earlier version of the Contact Loader dated 11/02/05 that is 224 KB in size. It should take care of this problem.*

**Q.** The Scalix Loader loads mail, but not calendar and a login popup name resolution window is displayed when the Calendar Loader is run.

**A.** *The user is most likely not logged on as the Eshuttle user or the Eshuttle user is not a member of the correct domain.*

**Q.** There is no calendar or contacts present in the mailboxes after migration.

**A.** *The Calendar and Contact Loaders are not launched automatically during the migration. Make sure to run the calendar and contact loaders after the mail loader has completed.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

**Q.** When loading mail into PST files, the Mail Loader loads mail for a while, then stops.

**A.** *Outlook 2000 has a 2 GB limit that might only allow for some of the data to be loaded when the bay file is larger than 2 GB. Outlook 2003 has no such size limit and can be used to circumvent this issue.*

**Q.** The Loader is unable to login and GW client is on the machine.

**A.** *You may have to split the GroupWise Extractor and Exchange Loader onto two separate machines. To do this, copy the Eshuttle directory onto a machine without GroupWise and use it for your loader machine. You will have to map a drive to the new machine from the loader machine and set the bay file directories to the new machine in order to run the extractor and loader simultaneously.*

**Q.** The Loader says it can't find the restart file.

**A.** *You need to clean out any restart information using Mission Control for the Loader. Run Mission Control for the Loader (econfig.exe) and in the Restart section, set the File and Key to blank and set the record to 0. Now Click Save and rerun the Loader.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Microsoft Exchange Loader

**Q.** The Exchange Loader loads mail, but not calendar and a login popup window is displayed when the Calendar Loader is run.

*A. The user is most likely not logged on as the Eshuttle user or the Eshuttle user is not a member of the correct domain or the Exchange Domain Servers group. The different data types use different APIs to access the mailboxes so it is possible for mail to work correctly and calendar to have insufficient access rights.*

**Q.** There is no calendar or contacts present in the mailboxes after migration.

*A. The Calendar and Contact Loaders are not launched automatically during the migration. Make sure to run the calendar and contact loaders after the mail loader has completed. To launch the calendar loader, run the escalndr.exe from the eshuttle/loader/exchange directory and to launch the contact loader, run escontct.exe.*

**Q.** The Loader is unable to login to mailboxes.

*A. Make sure you are logged into Windows as the Eshuttle user created above. Make sure that the Eshuttle user is a member of the correct group and is also a member of the same domain as the destination mailboxes.*

**Q.** The Loader is unable to login under Exchange 2003

*A. See the KB article above on setting correct rights for 2003. This can sometimes involve more than just setting the user in the Exchange Domain Servers group.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

**Q.** When running under Exchange 2003, the Mail Loader loads for a while, then starts throwing error messages regarding active mail.

**A.** Consult the Microsoft KB article

<http://support.microsoft.com/default.aspx?scid=kb;en-us;830836> for increasing the default mail and folder quantity limits in Exchange 2003.

**Q.** When loading mail into PST files, the Mail Loader loads mail for a while, then stops.

**A.** Outlook 2000 has a 2 GB limit that might only allow for some of the data to be loaded when the bay file is larger than 2 GB. Outlook 2003 has no such size limit and can be used to circumvent this issue.

**Q.** When loading mail into PST files, the PST files are not being created.

**A.** Make sure you aren't running the E-Mail Shuttle on the Exchange server or on a Windows server OS. These operating systems have documented problems with PST file creation. Also make sure that the Letter Age field in Mission Control for the Exchange Loader is set to -1 to enable the PST load.

**Q.** The Loader is unable to login and the GroupWise mail client is on the machine.

**A.** You may have to split the GroupWise Extractor and Exchange Loader onto two separate machines. To do this, copy the Eshuttle directory onto a machine without GroupWise and use it for your loader machine. You will have to map a drive to the new machine from the loader machine and set the bay file directories to the new machine in order to run the extractor and loader simultaneously. If GroupWise is not part of your migration, this problem can be fixed by uninstalling both the GroupWise mail client and Outlook and then reinstalling Outlook.



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

**Q.** The Loader says something about restart key mismatch and will not launch correctly.

*A. You need to clean out any restart information using Mission Control for the Loader. This is the EConfig.exe in the “eshuttle/loader/exchange” directory. Click on the Restart button and set all of the File and Key fields to blank and set all of the Record fields to 0. Then re-launch the loader. This is a common problem to see after a permissions problem prevents logging into to the destination mailboxes.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### Notes Loader

Q. The Notes Loader cannot login to the users Notes Database.

*A. Make sure that the last ID file used to login to the Notes client was an administrative ID file. Also make sure the Notes Client is not open when running the shuttle.*

Q. Certain .DLLs are not being located by my system, how can I fix them?

*A. The E-Mail Shuttle is looking for .DLLs in the directory or path of your Lotus Notes or Domino Server software. During the install of the product, you provided information that was written to the path of the system. Be certain that this information is correct by: At the DOS prompt (for example, "C:\"), type path and press Enter. The path for the Notes or Domino server should appear in the display. For example on the Domino Server, the default path is "C:\Lotus\Domino\". For a dedicated migration server running the Notes R5 client, the default path is "C:\Lotus\Notes\".*

### IMAP Loader

Q. How can I configure multiple instances of the E-Mail Shuttle to run simultaneously?

*A. Copy the distribution into unique directories on the migration server. Each directory should contain the executable files as well as the distinct configuration files for that migration instance.*

*For example, the E-Mail Shuttle instance managing the migration of the Marketing Department may be located at "C:\eshuttle\Marketing" while the E-Mail Shuttle instance managing the migration of the Human Resources Department may be located at "C:\eshuttle\HumanResources". Be aware that running multiple copies of the E-Mail Shuttle on a single PC will generally not help throughput due to bandwidth restrictions on a single NIC card.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

### **GroupWise Loader**

**Q.** The GroupWise Loader cannot login initially, but it does login successfully upon subsequent attempts.

*A. Increase the value for the PausePasswordReset parameter in Mission Control for the GroupWise Loader.*

**Q.** The GroupWise Loader is unable to reset the passwords of the mailboxes to be exported.

*A. Make sure you can reset the passwords manually. Also make sure you are logged into NDS as an administrator in both Netware and GroupWise. If NDS is not being used, password resets must be preformed manually prior to loading or the default password for all mailboxes must be known.*

**Q.** The GroupWise Loader cannot import Personal Address Books (PABs).

*A. If Outlook is on the migration machine, check the services for the Novell Default Settings mail profile and make sure that the Novell PABs service is enabled. Often this can be addressed by separating the extractor and loader to two separate PCs.*

**Q.** The bodies of very large messages are being truncated by the loader.

*A. This is due to an API limitation of 30,000 characters for message bodies. The API is unable to load message bodies larger than this size and these messages will be truncated. For reference, 30,000 characters are about 7 solid pages of text.*



## E-MAIL SHUTTLE USER GUIDE: Xandros Scalix Extractor

**Q.** The Sent Items folder was not migrated or migrated twice.

*A. This is due to differences in the way that Sent Items are handled in GroupWise versions 6.5 and above. Earlier versions of GroupWise deal with the Sent Items folder as a view of the Mailbox, where later versions treat Sent Items as a separate folder entirely. This can be adjusted in Mission Control for the GroupWise Loader under the Misc. tab. Check the box labeled “Target GW 6.5 or higher” if you are running version 6.5 or higher.*

**Q.** The days and months are being inverted on message dates.

*A. This is due to differences in date formatting in different regions of the world. This can be adjusted in Mission Control for the GroupWise Loader under the Misc. tab. The default is the US standard of (MM/DD/YYYY). Check the box labeled “Date Format (DD/MM/YYYY)” if you are experiencing this problem.*

**Q.** Our organization is not using NDS. Can we still use the E-Mail Shuttle to migrate users to GroupWise?

*A. Yes, the E-Mail Shuttle can still migrate users data, but NDS is required to automatically reset user passwords to a known default. Usually when loading into fresh empty mailboxes, this is not a problem as all mailboxes can be set to an identical default value and the password reset step is not required.*